



MASUNG printer Windows USB driver installation manual

Ver:2018/01/09


content

Notice	1
Step 1.....	2
Step 2.....	2
Step 3.....	3
Step 4.....	3
Step 5.....	4
Step 6.....	5
Step 7.....	6
Step 8.....	7
Step 9 Print a driver test page.....	8
Step 10 how to see printer USB port.....	10

Notice: this driver is suitable for windows XP/7/8/8.1/10 (including 32 bits and 64 bits)


Step 1

Open driver file offered by MASUNG sales, as below




Step 2

Run as administrator




Step 3

Choose [Yes] to continue



Step 4


Click [Next] to continue





Step 5

For the installation path, you are recommended to use the default path, but you also can choose your own path as you want.





Step 6

Choose correct “printer model”, Then click [Install] to continue.

Each Printer model represents different paper width.

1. W58(58mm) for 58mm paper width printers
2. W80(80mm) for 80mm paper width printers
3. W110(110mm) for 110 paper width printers


Product list as reference:

Paper width	Printer model	Auto cutter (Yes/No)
W58(58mm)	MSP-100	No
	MSP-100II	No
	MS-SP701	No
	MS-N58VB/VW/VH	Yes
	MS-D245	Yes
	MS-FPT201/201K	Yes
W80(80mm)	MS-800S(IP-100)	Yes
	MS-T500II	Yes
	MS-530I	Yes
	MS-T840/T850	Yes
	MS-G530/T890	Yes



	MS-D347&D347-TL&TH&THP&TLP&V&BE	Yes
	MS-FPT301/301K	Yes
	EP802-TU/TM/TMP	Yes
	GWK80	Yes
	MS-LP212	No
W110(110mm)	MS-2442	Yes

As below:




Step 7

the driver has been installed in PC successfully. Then click [OK] to finish its installation.




深圳市美松科技有限公司
SHENZHEN MASUNG TECHNOLOGY CO., LTD

Tel: +86-755-23283616
www.masungtek.com



Step 8

Enter into “ **Devices and Printers**” on PC and check driver installation result: there should be generated a printer icon, As below



Step 9 Print a driver test page


After printer driver installed successfully, please load thermal paper correctly.

A. Choose the Printer properties




深圳市美松科技有限公司
SHENZHEN MASUNG TECHNOLOGY CO., LTD

Tel: +86-755-23283616
www.masungtek.com



B. Click [Print Test Page]






深圳市美松科技有限公司
SHENZHEN MASUNG TECHNOLOGY CO., LTD

Tel: +86-755-23283616
www.masungtek.com

C. User gets driver test page, as below:




Step 10 how to see printer USB port

After driver has been installed successfully and printer has connected with user PC, then please open “Universal Serial Bus controllers” list that will show “USB printing Support” as below.




深圳市美松科技有限公司
SHENZHEN MASUNG TECHNOLOGY CO., LTD

Tel: +86-755-23283616
www.masungtek.com



Click [Properties]



Choose the [Children] option to see the connected USB port.



深圳市美松科技有限公司
SHENZHEN MASUNG TECHNOLOGY CO., LTD

Tel: +86-755-23283616
www.masungtek.com

